

ANSYS许可证管理器 安装步骤 - ANSYS 2022R1

开始安装

1. 将安装文件的压缩包，分别解压缩到不同的文件夹
2. 从解压缩后的一号盘点击setup.exe
3. 使用**管理员权限**运行安装程序


开始安装

- 点击“安装ANSYS许可证管理器”




安装过程

- 在弹出的警告点击 “ok”



安装过程


- 选择“我同意”，点击“下一步”






安装过程

- 设置安装路径后，点击“下一步”




安装过程

- 待安装产品如图所示设置，点击“下一步”




安装过程

- 检查如图所示设置，点击“下一步”




安装过程

- 程序开始安装，完成后点击“下一步”




安装过程

- 勾选“启动许可证管理中心”，点击“退出”



许可证管理器配置

- 完成后会自动打开浏览器，显示管理器页面
 - 也可以在开始菜单中的手动打开



开始菜单中点击此图标打开管理器网页


许可证管理器配置

- 在“增加许可证文件”页面，上传待使用的许可证文件



许可证管理器配置

- 在上传过程，弹出的提示中选择“安装许可证文件”



许可证管理器配置

- 安装成功后出现如图所示信息



许可证管理器配置

- 在“查看FlexNet许可”页面，可查看许可证信息（模块、数量、时间等）



Ansys License Manager Release 2022 R1

- Home
 - View Status/Start/Stop License Manager
 - Reread License Manager Settings
- License File Options
 - Add a License File
 - Get System Hostid Information
 - View FlexNet Licenses
- Log Files
 - View Licensing Interconnect Log
 - View FlexNet Debug Log
 - View License Management Center Log
- Reporting
 - View Current License Usage
 - View License Usage History
 - View Peak License Usage
 - View License Denials
- Diagnostics
 - Display FlexNet License Status
 - Gather Diagnostic Information

```

INCREMENT acpreppost ansyslmd 2023.0714 permanent 1 F50C288ACF29 \
  VENDOR_STRING=customer:01052089 SUPERSEDE ISSUER=SIEBEL \
  ISSUED=02-aug-2021 START=02-aug-2021 SIGN2="006E 22C7 F0EE \
  9BE5 34AF D7CE D856 3100 1493 C3A8 8492 4A8E F303 F6A4 3247"

INCREMENT advanced_meshing ansyslmd 2023.0714 permanent 1 \
  67EB7650DBAC VENDOR_STRING=customer:01052089 SUPERSEDE \
  ISSUER=SIEBEL ISSUED=02-aug-2021 START=02-aug-2021 SIGN2="0012 \
  D581 3E35 4595 1F2A 08CB 2DF2 AD00 D136 7172 499B 6D42 7E0C \
  C947 3D02"

INCREMENT ans_act ansyslmd 2023.0714 permanent 1 FF23B8ECCED0 \
  VENDOR_STRING=customer:01052089 SUPERSEDE ISSUER=SIEBEL \
  ISSUED=02-aug-2021 START=02-aug-2021 SIGN2="005A E89E 65F2 \
  0FBF 13DD 345F FA7C 7700 8A3C 3E86 9EBB EC77 411D 37A0 E1CC"

INCREMENT ansys ansyslmd 2023.0714 permanent 1 AEA7637C3E1D \
  VENDOR_STRING=customer:01052089 SUPERSEDE ISSUER=SIEBEL \
  ISSUED=02-aug-2021 START=02-aug-2021 SIGN2="0052 7CD6 335F \
  A057 DE10 9B7B 7B80 4000 60BF 792E FF5C E56D CAAB EA8C DB4B"

INCREMENT aqwa_pre ansyslmd 2023.0714 permanent 1 51EEFDB16506 \
  VENDOR_STRING=customer:01052089 SUPERSEDE ISSUER=SIEBEL \
  ISSUED=02-aug-2021 START=02-aug-2021 SIGN2="0088 7F4B 9CA0 \
  91A6 F5B8 8D4B 234B 5500 517E 475D 8005 6DE2 BA29 1C11 D8A6"

```

许可证的
详细内容

许可证管理器配置

- 查看许可证管理器运行状态，均为“运行中”



许可证管理器配置

- 在系统管理工具的服务管理工具中，将两个ANSYS开头的服务均设置为“自动启动”模式

Services (Local)

ANSYS Licensing Tomcat

[Stop](#) the service
[Restart](#) the service

Description:
 Apache Tomcat 9.0.37 Server - <https://tomcat.apache.org/>

Name	Description	Status	Startup Type	Log On As
ActiveX Installer (AxInstSV)	Provides User Account C...	Disabled	Disabled	Local System
AllJoyn Router Service	Routes AllJoyn message...	Running	Manual (Trigger Start)	Local Service
ANSYS Licensing Tomcat	Apache Tomcat 9.0.37 S...	Running	Automatic	Local System
ANSYS, Inc. License Manager	Handles license requests...	Running	Automatic	Local System
App Readiness	Gets apps ready for use t...	Running	Manual	Local System
Application Host Helper Service	Provides administrative ...	Running	Automatic	Local System
Application Identity	Determines and verifies t...	Running	Manual (Trigger Start)	Local Service
Application Information	Facilitates the running o...	Running	Manual (Trigger Start)	Local System
Application Layer Gateway Service	Provides support for 3rd ...	Running	Manual	Local Service
Application Management	Processes installation, re...	Running	Manual	Local System
AppX Deployment Service (AppXSVC)	Provides infrastructure s...	Running	Manual	Local System
Auto Time Zone Updater	Automatically sets the s...	Running	Disabled	Local Service
AVCTP service	This is Audio Video Cont...	Running	Manual (Trigger Start)	Local Service
Background Intelligent Transfer Service	Transfers files in the bac...	Running	Manual	Local System

防火墙白名单设置

- 许可证管理器需要设置防火墙白名单，以正常获取相关授权：
 - TCP 1055端口
 - TCP 2325端口
 - C:\Program Files\ANSYS Inc\Shared Files\Licensing\winx64\ansysli_server.exe
 - C:\Program Files\ANSYS Inc\Shared Files\Licensing\winx64\ansysli_client.exe
 - C:\Program Files\ANSYS Inc\Shared Files\Licensing\winx64\ansysli_monitor.exe
 - C:\Program Files\ANSYS Inc\Shared Files\Licensing\winx64\ansyslmd.exe
 - C:\Program Files\ANSYS Inc\Shared Files\Licensing\winx64\lmgrd.exe
- ANSYS客户端中将ansysli_client.exe加入防火墙的白名单中：
 - C:\Program Files\ANSYS Inc\Shared Files\Licensing\winx64\ansysli_client.exe
- 简单粗暴方法：将C:\Program Files\ANSYS Inc中的所有文件都加入防火墙白名单

THANK YOU

<http://www.emdoor.cn>
让前沿科技更平易近人

